

Platform Developer's Kit

PAL API Reference Manual



Celoxica, the Celoxica logo and Handel-C are trademarks of Celoxica Limited.

All other products or services mentioned herein may be trademarks of their respective owners.

Neither the whole nor any part of the information contained in, or the product described in, this document may be adapted or reproduced in any material form except with the prior written permission of the copyright holder.

The product described in this document is subject to continuous development and improvement. All particulars of the product and its use contained in this document are given by Celoxica Limited in good faith. However, all warranties implied or express, including but not limited to implied warranties of merchantability, or fitness for purpose, are excluded.

This document is intended only to assist the reader in the use of the product. Celoxica Limited shall not be liable for any loss or damage arising from the use of any information in this document, or any incorrect use of the product.

The information contained herein is subject to change without notice and is for general guidance only.

Copyright © 2003 Celoxica Limited. All rights reserved.

Authors: JAA, MA

Document number: RM-1150-1.2





Table of contents

Table of contents	
Conventions	3
Assumptions	
OMISSIONS	4
1. Introduction	
1.1 HEADER AND LIBRARY FILES	5
2. GENERIC API	6
2.1 Resource handles	6
2.2 Versioning	
2.2.1 API version numbers	
2.2.2 Library version information	
2.3 ERROR HANDLING	
2.4 GENERIC METHODS 2.4.1 Querying the number of resources	
2.4.1 Querying the number of resources	
2.4.3 Querying resource properties	
2.4.4 Running resources	10
2.4.5 Resetting resources	
2.4.6 Enabling and disabling resources	
2.4.7 Reading and writing resources	11
3. Resource-specific API	
3.1 LEDs (LED API)	
3.2 SEVEN-SEGMENT DISPLAYS (SEVENSEG API)	
3.3 BINARY SWITCHES AND BUTTONS (SWITCH API)	
3.4 GENERIC DATA I/O (DATAPORT API)	
3.5 PARALLEL PORTS (PARALLELPORT API)	
3.6 RS-232 SERIAL PORTS (RS232PORT API)	
3.7 PS/2 SERIAL PORTS (PS2PORT API)	
3.8 SINGLE-CYCLE RAMS (FASTRAM API)	
3.9 PIPELINED SINGLE-CYCLE RAMS (PL1RAM API)	
3.10 PIPELINED PL2 RAMs (PL2RAM API)	
3.11 RAMS WITHOUT GUARANTEED TIMING (SLOWRAM API)	
3.12 BLOCK STORAGE DEVICES (BLOCKSTORE API)	
3.13 VIDEO CAPTURE DEVICES (VIDEOIN API)	
3.14 VIDEO OUTPUT DEVICES (VIDEOOUT API)	
3.15 AUDIO INPUT DEVICES (AUDIOIN API)	35



Table of contents

3.16 AUDIO OUTPUT DEVICES (AUDIOOUT API)	36
3.17 ETHERNET DEVICES (ETHERNET API)	
I NDEX	

Conventions



Conventions

A number of conventions are used in this document. These conventions are detailed below.



Warning Message. These messages warn you that actions may damage your hardware.



Handy Note. These messages draw your attention to crucial pieces of information.

Hexadecimal numbers will appear throughout this document. The convention used is that of prefixing the number with '0x' in common with standard C syntax.

Sections of code or commands that you must type are given in typewriter font like this: voi d main();

Information about a type of object you must specify is given in italics like this: copy *SourceFileName DestinationFileName*

Optional elements are enclosed in square brackets like this: struct [type_Name]

Curly brackets around an element show that it is optional but it may be repeated any number of times.

string ::= "{character}"

Assumptions



Assumptions

This manual assumes that you:

- have used Handel-C or have the Handel-C Language Reference Manual
- are familiar with common programming terms (e.g. functions)
- are familiar with MS Windows

Omissions

This manual does not include:

- instruction in the use of place and route tools
- tutorial example programs. These are provided in the *PAL tutorial guide*.





1. Introduction

This reference manual describes the Celoxica Platform Abstraction Layer (PAL) Application Programming Interface (API).

The PAL API contains methods for accessing the following devices:

- LEDs
- Seven segment displays
- Switches
- Data ports
- Parallel ports
- RS-232 serial ports
- PS/2 ports
- Fast RAMs
- Pipelined RAMs
- Slow RAMs
- Block storage devices
- Video input devices
- Video output devices
- Audio input devices
- Audio output devices
- Ethernet devices

PAL defines a set of methods common to all of the devices. These are described in section 0. Device specific methods are described in the relevant section about that device.

1.1 Header and library files

The PAL distribution contains the header file pal . hch which contains the declarations of all the types and macros described in this document. All applications and libraries that use PAL should #i ncl ude this header.

Applications must link to the appropriate PAL library for the platform they are targeting. For instance, pal_rc100. hcl is needed to target the Celoxica RC100 board. This in turn requires the PSL library rc100. hcl and the standard library stdl i b. I i b. More information about choosing the appropriate libraries and header files is supplied in the PAL user manual.





2. Generic API

2.1 Resource handles

Pal Handle

Description The type

The type of references to PAL resources.

A Pal Handl e is used to distinguish a particular resource on a platform from the other resources of the same type. Handles to particular resources are obtained by the Pal X() and Pal XCT() family of macros. All macros that need to refer to a particular resource take a Pal Handl e as their first argument.

2.2 Versioning

2.2.1 API version numbers

macro expr Pal Versi onMaj or ();

Return value Integer constant.

Description Expression that returns the major component of the API version number.

For example, it would return 2 for API version 2.3.

Changes in the major version may add and remove functionality, or may change the behaviour of existing APIs. Code written with one major

number may or may not work with another.

macro expr Pal Versi onMi nor ();

Return value Integer constant.

Description Expression that returns the minor component of the API version number.

For example, it would return 3 for API version 2.3.

Changes in the minor version may add functionality to the API, but should not break existing code. New APIs are therefore backwards

compatible.





macro proc Pal Versi onRequire (Maj or, Mi nor);

Arguments *Maj or*: major API version number required.

Mi nor: minor API version number required.

Timing 0 clock cycles.

Description Procedure that fails with a compile-time assertion if the provided version

number is incompatible with the API version of the library it is linked

against.

Applications can ensure that they are compiling with a compatible API by calling Pal Versi onRequire(*Major*, *Minor*) with the major and minor

API version for which they were originally written.

2.2.2 Library version information

macro expr Pal VendorCode ();

Return value Integer constant.

Description Returns a specific integer code uniquely identifying a vendor.

Vendors should use their PCI vendor ID code if possible. For instance, Celoxica is 0x4144, Intel is 0x8086. Vendors without a PCI vendor ID code should use the space above 0x10000, contacting Celoxica before

releasing a library in order to avoid conflicts.

macro expr Pal VendorRel ease ();

Return value Integer constant.

Description Returns a vendor-specific integer code uniquely identifying a given

library and release number.

Applications typically only need to check vendor code and release number to provide source-level workarounds for known bugs in specific

library releases.

macro expr Pal VendorString ();

Return value String constant.

Description Returns a vendor specific string, primarily for use in debugging.





2.3 Error handling

Pal ErrorCode

Description

The type of PAL run-time error codes. Possible values are:

Value	Meaning
PAL_ERROR_OK	No error.
PAL_ERROR_I NVALI D_HANDLE	A method was passed a handle referring to a resource that is not of an allowed type for that method.
PAL_ERROR_DEVI CE_FAI LURE	A method has encountered physical device failure.

macro proc Pal ErrorHandl erRun (ErrorHandl erProc);

Pal ErrorCode.

Timing Terminates after executing ErrorHandl erProc(), if an error occurs.

Description This procedure runs indefinitely until a runtime error condition is

detected, at which point it calls the error handler procedure with the

error code as an argument.

The error handler procedure may, for example, reset the whole system

or drive some form of external error reporting (such as an LED).

2.4 Generic methods

2.4.1 Querying the number of resources

macro expr Pal XCount ();

Arguments None.

Return value Integer constant.

Description Expression that returns the total number of resources of type X on the

platform. The resources are not necessarily unique (the same physical

resource may be referred to by several indices).





macro expr Pal XUni queCount ();

Arguments None

Return value Integer constant.

Description Expression that returns the total number of unique resources of type X

on the platform. All unique resource indices map to distinct physical

resources.

macro proc Pal XRequi re (Count);

Arguments *Count*: integer constant.

Timing 0 clock cycles.

Description Checks that at least *Count* resources of type X are available at compile

time, and produces a suitable error message if not.

2.4.2 Getting resource handles

macro expr Pal X (Index);

Arguments *Index*: an unsigned intindex.

Return value Non-constant Pal Handl e.

Description Returns the *I ndex* numbered Pal Handl e from all resources of type X

available on the platform. *I ndex* need not be a constant. *I ndex* must be

in the range 0 to (Pal XCount () – 1) inclusive.

macro expr Pal XCT (IndexCT);

Arguments *IndexCT*: an integer constant index.

Return value Constant Pal Handle.

Description Returns the *IndexCT* numbered Pal Handle from all resources of type X

available on the platform. *Index* must be a constant in the range 0 to

(Pal XCount () - 1) inclusive.

2.4.3 Querying resource properties

macro expr Pal XGetMaxDataWidthCT ();

Arguments None.

Return value Integer constant.

Description Returns the maximum width of data that is to be passed to or from

resources of type X, at compile time. This is typically the width that

should be used for read and write methods.





macro expr Pal XGetDataWi dth (Handle);

Arguments Handle: Pal Handle to resource of type X.

Return value Integer value, evaluated at runtime.

Description Returns the actual width of data that is used by the handle referred to, at

runtime. Since this method works at runtime it can be used even when Handl e is not a constant (such as when it is passed through a function parameter). However, it cannot be used to set the width of variables. It may, for example, be used to choose suitable data formats at runtime.

macro expr Pal XGetDataWi dthCT (HandleCT);

Arguments Handl eCT: constant Pal Handl e to resource of type X.

Return value Integer compile-time constant for specifying a width.

Description Returns the actual width of data that is used by the handle referred to, at

compile time. Since this method works at compile time it can *only* be used where the PAL Handle is a constant, and can be deduced to be a constant by the DK compiler. So for instance, this cannot be used if *Handl eCT* is passed through a function parameter. However, since it returns a compile time constant it can be used to set variable widths and

do conditional compilation (using sel ect and i fsel ect).

2.4.4 Running resources

macro proc Pal XRun (HandleCT, ClockRate);

Arguments Handl eCT: constant Pal Handl e to resource of type X.

ClockRate: clock rate, in Hertz, of the domain in which the macro is

being called.

Timing Does not terminate in normal use.

Description Runs the device management tasks for resource X.

Must always run in parallel with Enable/Disable/Read/Write etc.

2.4.5 Resetting resources

macro proc Pal XReset (Handle);

Arguments Handle: Pal Handle to resource of type X.

Timing 0 or more clock cycles.

Description Resets the resource, i.e. brings the resource to a known state. As far as

possible this known state is the state of the resource immediately after initialization (this is not always possible for some peripherals). The

statement finishes executing once the reset is complete.

2. Generic API



2.4.6 Enabling and disabling resources

macro proc Pal XEnable (Handle);

Arguments Handle: Pal Handle to resource of type X.

Timing 0 or more clock cycles.

Description Enables the resource. This is typically needed to arbitrate between

shared resources, or resources on shared buses.

macro proc Pal XDi sable (Handle);

Arguments Handle: Pal Handle to resource of type X.

Timing 0 or more clock cycles.

Description Disables the resource. Reverses Pal XEnable ().

2.4.7 Reading and writing resources

macro proc Pal XRead (Handle, DataPtr);

Arguments Handle: Pal Handle to resource of type X.

DataPtr: pointer to an Ivalue (a writable resource, e.g. variable or signal) of the appropriate type. For many resources this is an unsigned

int of width (Pal XGetMaxDataWidthCT ()).

Timing 1 or more clock cycles.

Description Reads a single item of data from the resource, and stores it in the Ivalue

pointed at by DataPtr.

macro proc Pal XWrite (Handle, Data);

Arguments *Handle*: Pal Handle to resource of type X.

Data: expression of the appropriate type. For many uses this is an

unsigned int of width (Pal XGetMaxDataWidthCT ()).

Timing 1 or more clock cycles.

Description Statement that writes a single item of data to the resource.



3. Resource-specific API

3.1 LEDs (LED API)

The LED API supports simple binary LEDs. More complex LEDs (such as multicolour) can be supported by using several LED resources in conjunction, or via the data port API.

```
macro expr Pal LED (Index);
see macro expr Pal X ();
macro expr Pal LEDCT (Index);
see macro expr Pal XCT (Index);
macro expr Pal LEDCount ();
see macro expr Pal XCount ();
macro expr Pal LEDUni queCount ();
see macro expr Pal XUni queCount ();
macro proc Pal LEDRequire (Count);
see macro proc Pal XRequire (Count);
macro proc Pal LEDWrite (Handle, Data);
              Handle: Pal Handle to an LED resource.
Arguments
              Data: expression of type unsigned 1.
Timing
              1 clock cycle.
Description
              Statement, Turns an LED on or off. A value of 1 means on, 0 means off.
```

3.2 Seven-segment displays (SevenSeg API)

The seven-segment display API supports standard seven-segment (plus decimal point) displays. More complex displays can be supported via the data port API.

```
macro expr Pal SevenSeg (Index);
see macro expr Pal SevenSegCT (Index);
see macro expr Pal XCT (Index);
macro expr Pal SevenSegCount ();
see macro expr Pal XCount ();
macro expr Pal SevenSegUni queCount ();
see macro expr Pal SevenSegUni queCount ();
```



macro proc Pal SevenSegRequi re (Count);

see macro proc Pal XRequire (Count);

macro proc Pal SevenSegEnable (Handle);

see macro expr Pal XEnable (Handle);

macro proc Pal SevenSegDi sable (Handle);

see macro expr Pal XDi sable (Handle);

macro proc Pal SevenSegWri teShape (Handle, ShapeMask);

Arguments Handle: Pal Handle to a SevenSeg resource.

ShapeMask: expression of type unsigned 8.

Timing 1 clock cycle.

Description Set a particular shape in the seven-segment display. *ShapeMask* is a

binary mask where 1 means ON and 0 means OFF. Each of the eight bits corresponds to a segment of the display (7-segments for the digit and

one for the decimal point).

macro proc Pal SevenSegWriteDigit (Handle, Value, Decimal Point);

Arguments Handle: Pal Handle to resource of type X.

Value: expression of type unsigned 4.

DecimalPoint: expression of type unsigned 1.

Timing 1 clock cycle.

Description Set a particular hexadecimal digit in the seven-segment display. Value is

the hex value, and *Deci mal Point* specifies whether the decimal point

should be turned on (1) or off (0).

3.3 Binary switches and buttons (Switch API)

The switch API supports simple binary switches or buttons, typically used for debugging. More complex switches can be supported via the data port API.

macro expr Pal Swi tch (Index);

see macro expr Pal X (*Index*);

macro expr Pal SwitchCT (Index);

see macro expr Pal XCT (Index);

macro expr Pal SwitchCount ();

see macro expr Pal XCount ();

macro expr Pal Swi tchUni queCount ();

see macro expr Pal XUni queCount ();



macro proc Pal Swi tchRequire (Count);

see macro proc Pal XRequire (Count);

macro proc Pal Swi tchRead (Handle, DataPtr);

Arguments *Handl e*: Pal Handl e to a Switch resource.

DataPtr: pointer to an Ivalue (e.g. variable or signal) of type unsigned

1.

Timing 1 clock cycle.

Description Read the current state of a switch. A value of 1 means ON (or closed), a

value of 0 means OFF (or open).

3.4 Generic data I/O (DataPort API)

The data port API supports generic bi- or uni-directional data I/O.

macro expr Pal DataPort (Index);

see Pal X (Index);

macro expr Pal DataPortCT (Index);

see Pal XCT (Index);

macro expr Pal DataPortCount ();

see macro expr Pal XCount ();

macro expr Pal DataPortUni queCount ();

see macro expr Pal XUni queCount ();

macro proc Pal DataPortRequi re (Count);

see macro proc Pal XRequire (Count);

macro expr Pal DataPortGetMaxDataWidthCT ();

see macro expr Pal XGetMaxDataWidthCT ();

macro expr Pal DataPortGetDataWi dth (Handle);

see macro expr Pal XGetDataWidth (Handle);

macro expr Pal DataPortGetDataWi dthCT (HandleCT);

see macro expr Pal XGetDataWidthCT (HandleCT);

macro proc Pal DataPortRun (HandleCT, ClockRate);

see macro proc Pal XRun (HandleCT, ClockRate);

macro proc Pal DataPortReset (Handle);

see macro proc Pal XReset (Handle);

macro proc Pal DataPortEnable (Handle);

see macro proc Pal XEnable (Handle);

macro proc Pal DataPortDi sabl e (Handl e);

see macro proc Pal XDi sable (Handle);



macro proc Pal DataPortRead (Handle, DataPtr);

Arguments Handle: Pal Handle to a DataPort resource.

DataPtr: pointer to an Ivalue (e.g. variable or signal) of type unsigned

(Pal DataPortGetMaxDataWidthCT ()).

Timing 1 or more clock cycles.

Description Reads a single item of data from the data port, and stores it in the Ivalue

pointed at by DataPtr.

macro proc Pal DataPortWrite (Handle, Data);

Arguments Handle: Pal Handle to a DataPort resource.

Data: expression of type unsigned (Pal DataPortGetMaxDataWidthCT

()).

Timing 1 or more clock cycles.

Description Writes a single item of data to the data port.

3.5 Parallel ports (ParallelPort API)

These methods are used only for getting handles to parallel ports, which otherwise implement the DataPort API.

macro expr Pal Paral | el Port (Index);

see Pal X (Index);

macro expr Pal Paral | el PortCT (Index);

see Pal XCT (Index);

macro expr Pal Paral I el PortCount ();

see macro expr Pal XCount ();

macro expr Pal Paral I el PortUni queCount ();

see macro expr Pal XUni queCount ();

macro proc Pal Paral I el PortRequi re (Count);

see macro proc Pal XRequire (Count);

3.6 RS-232 serial ports (RS232Port API)

These methods are used only for getting handles to RS-232 serial ports, which otherwise implement the DataPort API.

macro expr Pal RS232Port (Index);

see Pal X (*Index*);



```
macro expr Pal RS232PortCT (Index);
see Pal XCT (Index);

macro expr Pal RS232PortCount ();
see macro expr Pal XCount ();

macro expr Pal RS232PortUni queCount ();
see macro expr Pal XUni queCount ();

macro proc Pal RS232PortRequi re (Count);
see macro proc Pal XRequi re (Count);
```

3.7 PS/2 serial ports (PS2Port API)

These methods are used only for getting handles to PS/2 serial ports, which otherwise implement the DataPort API.

```
macro expr Pal PS2Port (Index);
see Pal X (Index);

macro expr Pal PS2PortCT (Index);
see Pal XCT (Index);

macro expr Pal PS2PortCount ();
see macro expr Pal XCount ();

macro expr Pal PS2PortUni queCount ();
see macro expr Pal XUni queCount ();
see macro proc Pal PS2PortRequi re (Count);
see macro proc Pal XRequi re (Count);
```

3.8 Single-cycle RAMs (FastRAM API)

FastRAMs are single-cycle RAMs that can be read from or written to in exactly one clock cycle, hence they are fast in terms of clock cycles taken. However, FastRAMs often have lower performance than pipelined PL1RAMs since they rely on a very short combinational path through the entire RAM access circuitry. The FastRAM API is suitable for standard asynchronous static RAMs.

```
macro expr Pal FastRAM (Index);
see Pal X (Index);

macro expr Pal FastRAMCT (Index);
see Pal XCT (Index);

macro expr Pal FastRAMCount ();
see macro expr Pal XCount ();

macro expr Pal FastRAMUni queCount ();
see macro expr Pal XUni queCount ();
```



macro proc Pal FastRAMRequire (Count);

see macro proc Pal XRequire (Count);

macro expr Pal FastRAMGetMaxDataWidthCT ();

see macro expr Pal XGetMaxDataWidthCT ();

macro expr Pal FastRAMGetMaxAddressWi dthCT ();

Arguments None.

Return value Integer compile-time constant for specifying a width.

Returns the maximum width of the address bus of the RAM, at compile Description

time. This is the width that should be used for the address parameter to

the RAM read and write methods.

macro expr Pal FastRAMGetDataWidth (Handle);

see macro expr Pal XGetDataWidth (Handle);

macro expr Pal FastRAMGetAddressWidth (Handle);

Handle: Pal Handle to FastRAM resource. Arguments

Return value Integer value, evaluated at runtime.

Description Returns the actual width of the address bus of the RAM that is used by

the handle referred to, at runtime. Since this method works at runtime it can be used even when Handle is not a constant (such as when it is passed through a function parameter). However, it cannot be used to set

the width of variables.

macro expr Pal FastRAMGetDataWi dthCT (HandleCT):

see macro expr Pal XGetDataWidthCT (HandleCT);

macro expr Pal FastRAMGetAddressWi dthCT (HandleCT);

Arguments HandleCT: constant Pal Handle to FastRAM resource.

Integer compile-time constant for specifying a width. Return value

Description Returns the actual width of the address bus of the RAM that is used by

the handle referred to, at compile time. Since this method works at compile time it can *only* be used where *Handle* is a constant, and can be deduced to be a constant by the DK compiler. So for instance, this cannot be used if *Handle* is passed through a function parameter. However, since it returns a compile-time constant it can be used to set variable widths and do conditional compilation (using select and

ifselect).

macro proc Pal FastRAMRun (HandleCT, ClockRate);

see macro expr Pal XRun (HandleCT, ClockRate);



macro proc Pal FastRAMReset (Handle);

see macro expr Pal XReset (Handle);

macro proc Pal FastRAMEnable (Handle);

see macro expr Pal XEnable (Handle);

macro proc Pal FastRAMDi sable (Handle);

see macro expr Pal XDi sable (Handle);

macro proc Pal FastRAMRead (Handle, Address, DataPtr);

Arguments *Handl e*: Pal Handl e to FastRAM resource.

Address: Address of data to read, of type unsigned

(Pal FastRAMGetMaxAddressWidthCT ()).

DataPtr: pointer to an Ivalue (e.g. variable or signal) of type unsigned

(Pal FastRAMGetMaxDataWidthCT ()).

Timing 1 clock cycle.

Description Reads a single item of data from the RAM at the specified address, and

stores it in the Ivalue pointed at by DataPtr.

macro proc Pal FastRAMWrite (Handle, Address, Data);

Arguments *Handl e*: Pal Handl e to FastRAM resource.

Address: Address of data to be written, of type unsigned

(Pal FastRAMGetMaxAddressWidthCT ()).

Data: expression of type unsigned (Pal FastRAMGetMaxDataWidthCT

()).

Timing 1 clock cycle.

Description Writes a single item of data to the RAM at the specified address.

3.9 Pipelined single-cycle RAMs (PL1RAM API)

PL1RAMs are RAMs that can be read from or written to in exactly one clock cycle, but with the address supplied one cycle earlier (and hence pipelined). This is typically a fast way of accessing RAMs (in terms of combinational path length). The PL1RAM API is suitable for standard zero bus turnaround (ZBT) synchronous static RAM.

macro expr Pal PL1RAM (Index);

see macro expr Pal X (Index);

macro expr Pal PL1RAMCT (Index);

see macro expr Pal XCT (Index);

macro expr Pal PL1RAMCount ();

see macro expr Pal XCount ();



macro expr Pal PL1RAMUni queCount (); see macro expr Pal XUni queCount (); macro proc Pal PL1RAMPortRequire (Count); see macro proc Pal XRequire (*Count*); macro expr Pal PL1RAMGetMaxDataWidthCT (); see macro expr Pal XGetMaxDataWidthCT (); macro expr Pal PL1RAMGetMaxAddressWi dthCT (); see macro expr PALFastRAMGetMaxAddressWidthCT (); macro expr Pal PL1RAMGetDataWidth (Handle); see macro expr Pal XGetDataWidth (Handle); macro expr Pal PL1RAMGetAddressWi dth (Handle): see macro expr Pal FastRAMGetAddressWidth (Handle); macro expr Pal PL1RAMGetDataWi dthCT (HandleCT); see macro expr Pal XGetDataWidthCT (HandleCT); macro expr Pal PL1RAMGetAddressWi dthCT (HandleCT); see macro expr Pal FastRAMGetAddressWidthCT (HandleCT); macro proc Pal PL1RAMRun (HandleCT, ClockRate); see macro expr Pal XRun (HandleCT, ClockRate); macro proc Pal PL1RAMReset (Handle); see macro expr Pal XReset (Handle); macro proc Pal PL1RAMEnable (Handle); see macro expr Pal XEnable (Handle); macro proc Pal PL1RAMDi sable (Handle): see macro expr Pal XDi sable (Handle); macro proc Pal PL1RAMSetReadAddress (Handle, Address); Arguments Handle: Pal Handle to a PL1RAM resource. Address: Address of data to read, of type unsigned (Pal PL1RAMGetMaxAddressWi dthCT ()). Timing 1 clock cycle. Description Sets the address for a read that will occur on the next clock cycle.



macro proc Pal PL1RAMSetWri teAddress (Handle, Address);

Arguments Handle: Pal Handle to a PL1RAM resource.

Address: Address of data to be written, of type unsigned

(Pal PL1RAMGetMaxAddressWi dthCT ()).

Timing 1 clock cycle.

Description Sets the address for a write that will occur on the next clock cycle.

macro proc Pal PL1RAMRead (Handle, DataPtr);

Arguments *Handl e*: Pal Handl e to a PL1RAM resource.

DataPtr: pointer to an Ivalue (e.g. variable or signal) of type unsigned

(Pal PL1RAMGetMaxDataWidthCT ()).

Timing 1 clock cycle.

Description Reads a single item of data from the address in the RAM set by

Pal PL1RAMSetReadAddress on the previous clock cycle, and stores it in

the Ivalue pointed at by DataPtr.

macro proc Pal PL1RAMWrite (Handle, Data);

Arguments Handle: Pal Handle to a PL1RAM resource.

Data: expression of type unsigned (Pal PL1RAMGetMaxDataWidthCT ()).

Timing 1 clock cycle.

Description Writes a single item of data to the RAM at the address set by

Pal PL1RAMSetWri teAddress on the previous clock cycle.

3.10 Pipelined PL2 RAMs (PL2RAM API)

PL2RAMs are similar to PL1 RAMs but there are two clock cycles between setting the address and reading/writing data. The RAMs can be read from or written to in exactly one clock cycle, but with the address supplied two cycles earlier. This is typically a fast way of accessing RAMs

Some platforms, such as the ADM-XRC-II (RC2000) do not support PL1 RAMs. However, platforms which do support PL1 RAMs also support PL2 RAMs, so you can make your code more portable by using PL2 RAMs.

macro expr Pal PL2RAM (Index);

see macro expr Pal X (*Index*);

macro expr Pal PL2RAMCT (Index);

see macro expr Pal XCT (Index);

macro expr Pal PL2RAMCount ();

see macro expr Pal XCount ();



```
macro expr Pal PL2RAMUni queCount ();
see macro expr Pal XUni queCount ();
macro proc Pal PL2RAMPortRequire (Count);
see macro proc Pal XRequire (Count);
macro expr Pal PL2RAMGetMaxDataWidthCT ();
see macro expr Pal XGetMaxDataWidthCT ();
macro expr Pal PL2RAMGetMaxAddressWi dthCT ();
see macro expr PALFastRAMGetMaxAddressWidthCT ();
macro expr Pal PL2RAMGetDataWidth (Handle);
see macro expr Pal XGetDataWidth (Handle);
macro expr Pal PL2RAMGetAddressWi dth (Handle):
see macro expr Pal FastRAMGetAddressWidth (Handle);
macro expr Pal PL2RAMGetDataWi dthCT (HandleCT);
see macro expr Pal XGetDataWidthCT (HandleCT);
macro expr Pal PL2RAMGetAddressWi dthCT (HandleCT);
see macro expr Pal FastRAMGetAddressWidthCT (HandleCT);
macro proc Pal PL2RAMRun (HandleCT, ClockRate);
see macro expr Pal XRun (HandleCT, ClockRate);
macro proc Pal PL2RAMReset (Handle);
see macro expr Pal XReset (Handle);
macro proc Pal PL2RAMEnable (Handle);
see macro expr Pal XEnable (Handle);
macro proc Pal PL2RAMDi sable (Handle):
see macro expr Pal XDi sable (Handle);
macro proc Pal PL2RAMSetReadAddress (Handle, Address);
Arguments
             Handle: Pal Handle to a PL2RAM resource.
             Address: Address of data to read, of type unsigned
              (Pal PL2RAMGetMaxAddressWidthCT ()).
Timing
             1 clock cycle.
Description
             Sets the address for a read that will occur two clock cycles later. For
             example:
             seq
              {
                  Pal PL2RAMSetReadAddress (Handle, Addr);
                  del ay;
                  Pal PL2RAMRead (Handle, &Data);
             }
```



macro proc Pal PL2RAMSetWri teAddress (Handle, Address);

Arguments Handle: Pal Handle to a PL2RAM resource.

Address: Address of data to be written, of type unsigned

(Pal PL2RAMGetMaxAddressWi dthCT ()).

Timing 1 clock cycle.

Description Sets the address for a write that will occur two clock cycles later.

macro proc Pal PL2RAMRead (Handle, DataPtr);

Arguments *Handl e*: Pal Handl e to a PL2RAM resource.

DataPtr: pointer to an Ivalue (e.g. variable or signal) of type unsigned

(Pal PL2RAMGetMaxDataWidthCT ()).

Timing 1 clock cycle.

Description Reads a single item of data from the address in the RAM set by

Pal PL2RAMSetReadAddress two clock cycles earlier, and stores it in the

Ivalue pointed at by DataPtr.

macro proc Pal PL2RAMWrite (Handle, Data);

Arguments Handle: Pal Handle to a PL2RAM resource.

Data: expression of type unsigned (Pal PL2RAMGetMaxDataWidthCT ()).

Timing 1 clock cycle.

Description Writes a single item of data to the RAM at the address set by

Pal PL2RAMSetWri teAddress two clock cycles earlier.

3.11 RAMs without guaranteed timing (SlowRAM API)

SlowRAMs are RAMs that can be read from or written to in multiple cycles. This is the most generic and platform independent interface to RAMs and other random access storage devices. This API would be suitable for accessing shared RAMs arbitrated by some external circuitry, or for accessing RAMs which cannot guarantee timing due to refresh constraints (such as DRAM).

macro expr Pal SlowRAM (Index);

see macro expr Pal X (Index);

macro expr Pal SI owRAMCT (Index);

see macro expr Pal XCT (Index);

macro expr Pal SI owRAMCount ();

see macro expr Pal XCount ();



macro expr Pal SI owRAMUni queCount (); see macro expr Pal XUni queCount (); macro proc Pal SI owRAMRequire (Count); see macro proc Pal XRequire (Count); macro expr Pal SI owRAMGetMaxDataWi dthCT (); see macro expr Pal XGetMaxDataWidthCT (); macro expr Pal SI owRAMGetMaxAddressWi dthCT (): see macro expr Pal FastRAMGetMaxAddressWidthCT (); macro expr Pal SlowRAMGetDataWidth (Handle); see macro expr Pal XGetDataWidth (Handle); macro expr Pal SI owRAMGetAddressWi dth (Handle); see macro expr PALFastRAMGetAddressWidth (Handle); macro expr Pal SI owRAMGetDataWi dthCT (HandleCT); see macro expr Pal XGetDataWidthCT (HandleCT); macro expr Pal SI owRAMGetAddressWi dthCT (HandleCT); see macro expr Pal FastRAMGetAddressWidthCT (HandleCT); macro proc Pal SI owRAMRun (HandleCT, ClockRate); see macro proc Pal XRun (HandleCT, ClockRate); macro proc Pal SI owRAMReset (Handle); see macro proc Pal XReset (Handle); macro proc Pal SI owRAMEnable (Handle); see macro proc Pal XEnable (Handle); macro proc Pal SI owRAMDi sable (Handle); see macro proc Pal XDi sable (Handle); macro proc Pal SI owRAMRead (Handle, Address, DataPtr); Handle: Pal Handle to a SlowRAM resource. Arguments Address: Address of data to read, of type unsigned (Pal SI owRAMGetMaxAddressWidthCT ()). DataPtr: pointer to an Ivalue (e.g. variable or signal) of type unsigned (Pal SI owRAMGetMaxDataWi dthCT ()). **Timing** 1 or more clock cycles. Description Reads a single item of data from the RAM at the specified address, and stores it in the Ivalue pointed at by *DataPtr*.



macro proc Pal SlowRAMWrite (Handle, Address, Data);

Arguments Handle: Pal Handle to SlowRAM resource.

Address: Address of data to be written, of type unsigned

(Pal SI owRAMGetMaxAddressWidthCT ()).

Data: expression of type unsigned (Pal SI owRAMGetMaxDataWi dthCT

()).

Timing 1 or more clock cycles.

Description Writes a single item of data to the RAM at the specified address.

3.12 Block storage devices (BlockStore API)

PalBlockStore is typically used by devices that have block oriented access, and in particular require the user to erase a block of one or more locations before writing new data, such as Flash memory. The address space is treated as being the contiguous concatenation of all of the blocks, i.e. address location 0 is first entry in block 0, address location (Pal Bl ockStoreGetBl ockLength (*Handl e*)) is the first entry in block 1.

macro expr Pal Bl ockStore (Index);

see macro expr Pal X (*Index*);

macro expr Pal Bl ockStoreCT (Index);

see macro expr Pal XCT (Index);

macro expr Pal Bl ockStoreCount ();

see macro expr Pal XCount ();

macro expr Pal Bl ockStoreUni queCount ();

see macro expr Pal XUni queCount ();

macro proc Pal Bl ockStoreRequi re (Count);

see macro proc Pal XRequire (Count);

macro expr Pal Bl ockStoreGetMaxDataWidthCT ();

see macro expr Pal XGetMaxDataWi dthCT ();

macro expr Pal Bl ockStoreGetMaxAddressWi dthCT ();

see macro expr PALFastRAMGetMaxAddressWidthCT ();

macro expr Pal Bl ockStoreGetMaxBl ockLengthCT ();

Arguments None.

Return value Integer compile-time constant for specifying a width.

Description Returns the maximum length of a block for all of the block store devices

on the platform, at compile time. This is typically, but not always, a

power of two.



macro expr Pal Bl ockStoreGetDataWi dth (Handle);

see macro expr Pal XGetDataWidth (Handle);

macro expr Pal Bl ockStoreGetAddressWi dth (Handle);

see macro expr Pal FastRAMGetAddressWidth (Handle);

macro expr Pal Bl ockStoreGetBl ockLength (Handle);

Arguments Handle: Pal Handle to a BlockStore resource.

Return value Integer value evaluated at runtime.

Description Returns the actual length of a block for the block store device used by

the handle referred to, at runtime. Since this method works at runtime it can be used even when *Handle* is not a constant (such as when it is passed through a function parameter). However, it cannot be used to set

the width of variables.

macro expr Pal Bl ockStoreGetDataWi dthCT (Handl eCT);

see macro expr Pal XGetDataWidthCT (HandleCT);

macro expr Pal Bl ockStoreGetAddressWi dthCT (Handl eCT);

see macro expr PalFastRAMGetAddressWidthCT (HandleCT);

macro expr Pal Bl ockStoreGetBl ockLengthCT (HandleCT);

Arguments *Handl eCT*: constant Pal Handl e to a BlockStore resource.

Return value Integer compile-time constant for specifying a width.

Description Returns the actual length of a block for the block storage device that is

used by the handle referred to, at compile time. Since this method works at compile time it can only be used where *Handle* is a constant, and can be deduced to be a constant by the DK compiler. So for instance, this cannot be used if *Handle* is passed through a function parameter. However, since it returns a compile time constant it can be used to set variable widths and do conditional compilation (using select and

ifselect).

macro proc Pal Bl ockStoreRun (Handl eCT, Cl ockRate);

see macro proc Pal XRun (HandleCT, ClockRate);

macro proc Pal Bl ockStoreReset (Handle);

see macro proc Pal XReset (Handle);

macro proc Pal Bl ockStoreEnable (Handle);

see macro proc Pal XEnable (Handle);

macro proc Pal Bl ockStoreDi sable (Handle);

see macro proc Pal XDi sable (Handle);



macro proc Pal BlockStoreRead (Handle, Address, DataPtr);

Arguments Handle: Pal Handle to a BlockStore resource.

Address: Address of data to read, of type unsigned (Pal Bl ockStoreGetMaxAddressWi dthCT ()).

DataPtr: pointer to an Ivalue (e.g. variable or signal) of type unsigned

(Pal Bl ockStoreGetMaxDataWidthCT ()).

Timing 1 or more clock cycles.

Description Reads a single item of data from the block store device at the specified

address, and stores it in the Ivalue pointed at by DataPtr.

macro proc Pal BlockStoreWrite (Handle, Address, Data);

Arguments Handle: Pal Handle to a BlockStore resource.

Address: Address of data to be written, of type unsigned

(Pal Bl ockStoreGetMaxAddressWi dthCT ()).

Data: expression of type unsigned (Pal Bl ockStoreGetMaxDataWi dthCT

()).

Timing 1 or more clock cycle.

Description Writes a single item of data to the block store device at the specified

address.

macro proc Pal Bl ockStoreEraseBl ock (Handle, Bl ockNumber);

Arguments Handle: Pal Handle to a BlockStore resource.

BlockNumber: Index of the block to erase, of type unsigned

(Pal Bl ockStoreGetMaxAddressWi dthCT ()-

log2floor (PalBlockStoreGetMaxBlockLengthCT)).

Timing 1 or more clock cycles.

Description Statement that erases a complete block indexed by *BI ockNumber* from

the block store device used by *Handle* to prepare it for re-writing.

3.13 Video capture devices (VideoIn API)

The VideoIn API supports generic video capture devices.

macro expr Pal Vi deol n (Index);

see macro expr Pal X (Index);

macro expr Pal Vi deol nCT (Index);

see macro expr Pal XCT (*Index*);



macro expr Pal Vi deol nCount ();

see macro expr Pal XCount ();

macro expr Pal Vi deol nUni queCount ();

see macro expr Pal XUni queCount ();

macro proc Pal Vi deol nRequire (Count);

see macro proc Pal XRequire (Count);

macro expr Pal Vi deol nGetMaxXWi dthCT ();

Arguments None.

Return value
Integer compile-time constant for specifying a width.

Description Returns the maximum width of the X co-ordinate of all of the video input

devices on the platform, at compile time. This is the width that should be used for the Ivalue that is pointed to by *XPtr* in the Pal Vi deol nRead

method.

macro expr Pal Vi deol nGetMaxYWi dthCT ();

Arguments None.

Return value Integer compile-time constant for specifying a width.

Description Returns the maximum width of the Y co-ordinate of all of the video input

devices on the platform, at compile time. This is the width that should be used for the Ivalue that is pointed to by *YPtr* in the Pal Vi deol nRead

method.

macro expr Pal Vi deol nGetMaxCol orWi dthCT ();

Arguments None.

Return value
Integer compile-time constant for specifying a width.

Description Returns the maximum width of the pixel colour of all of the video input

devices on the platform, at compile-time. This is the width that should be used for the Ivalue that is pointed to by *Pi xel Ptr* in the Pal Vi deol nRead

method.

macro expr Pal Vi deol nGetXWi dth (Handle);

Arguments Handle: Pal Handle to a VideoIn resource.

Return value Integer value evaluated at runtime.

Description Returns the actual width of the X co-ordinate of the video input device

used by the handle referred to, at runtime. Since this method works at runtime it can be used even when *Handle* is not a constant (such as when it is passed through a function parameter). However, it cannot be

used to set the width of variables.



macro expr Pal Vi deol nGetYWi dth (Handle);

Arguments Handle: Pal Handle to a VideoIn resource.

Return value

Integer value evaluated at runtime.

Description Returns the actual width of the Y co-ordinate of the video input device

used by the handle referred to, at runtime. Since this method works at runtime it can be used even when Handle is not a constant (such as when it is passed through a function parameter). However, it cannot be

used to set the width of variables.

macro expr Pal Vi deol nGetCol orWi dth (Handle);

Arguments Handle: Pal Handle to a VideoIn resource.

Return value

Integer value evaluated at runtime.

Description Returns the actual width of the pixel colour of the video input device

used by the handle referred to, at runtime. Since this method works at runtime it can be used even when *Handle* is not a constant (such as when it is passed through a function parameter). However, it cannot be

used to set the width of variables.

macro expr Pal Vi deol nGetXWi dthCT (Handl eCT);

Arguments Handl eCT: constant Pal Handl e to a VideoIn resource.

Return value Integer compile-time constant for specifying a width.

Description Returns the actual width of the X co-ordinate of the video input device

that is used by the handle referred to, at compile-time.

Since this method works at compile time it can only be used where *Handl eCT* is a constant, and can be deduced to be a constant by the DK compiler. So for instance, this cannot be used if *Handl eCT* is passed through a function parameter. However, since it returns a compile time constant it can be used to set variable widths and do conditional

compilation (using sel ect and i fsel ect).



macro expr Pal Vi deol nGetYWi dthCT (Handl eCT);

Arguments Handl eCT: constant Pal Handl e to a VideoIn resource.

Return value Integer compile-time constant for specifying a width.

Description Returns the actual width of the Y co-ordinate of the video input device

that is used by the handle referred to, at compile-time.

Since this method works at compile time it can *only* be used where *Handl eCT* is a constant, and can be deduced to be a constant by the DK compiler. So for instance, this cannot be used if *Handl eCT* is passed through a function parameter. However, since it returns a compile time constant it can be used to set variable widths and do conditional

compilation (using select and ifselect)

macro expr Pal Vi deol nGetCol orWi dthCT (Handl eCT);

Arguments Handl eCT: constant Pal Handl e to a VideoIn resource.

Return value Compile-time constant unsigned int for specifying a width.

Description Returns at the actual width of the pixel color of the video input device

that is used by the handle referred to, compile-time. Since this method works at compile time it can *only* be used where *HandleCT* is a constant, and can be deduced to be a constant by the DK compiler. So for instance, this cannot be used if *HandleCT* is passed through a function

parameter. However, since it returns a compile time constant it can be used to set variable widths and do conditional compilation (using sel ect

and i fsel ect)

macro proc Pal Vi deol nRun (HandleCT, ClockRate);

see macro proc Pal XRun (HandleCT, ClockRate);

macro proc Pal Vi deol nReset (Handle);

see macro proc Pal XReset (Handle);

macro proc Pal Vi deol nEnable (Handle);

see macro proc Pal XEnable (Handle);

macro proc Pal Vi deol nDi sable (Handle);

see macro proc Pal XDi sable (Handle);



macro proc Pal Vi deol nRead (Handle, XPtr, YPtr, Pixel Ptr);

Arguments Handle: Pal Handle to a VideoIn resource.

XPtr: Pointer to an Ivalue, of type unsigned

(Pal Vi deol nGetMaxXWi dthCT ()).

YPtr: Pointer to an Ivalue, of type unsigned

(Pal Vi deol nGetMaxYWi dthCT ()).

Pixel Ptr: pointer to an Ivalue (e.g. variable or signal) of type unsigned

(Pal Vi deol nGetMaxCol orWi dthCT ()).

Timing 1 or more clock cycles.

Description Reads a single pixel from the video input device. The call sets both the

color value in PixelPtr and the X and Y coordinates of the captured pixel in XPtr and YPtr. Frames may be interlaced. This function needs to be called repeatedly without delay in order to be sure of not missing pixels.

The video format is typically 888 RGB, giving a width of 24.

3.14 Video output devices (VideoOut API)

The VideoOut API supports generic progressive scan video output, such as VGA.

macro expr Pal Vi deoOut (Index);

see macro expr Pal X (Index);

macro expr Pal Vi deoOutCT (Index);

see macro expr Pal XCT (Index);

macro expr Pal Vi deoOutCount ();

see macro expr Pal XCount ();

macro expr Pal Vi deoOutUni queCount ();

see macro expr Pal XUni queCount ();

macro proc Pal Vi deoOutRequi re (Count);

see macro proc Pal XRequire (Count);

macro expr Pal Vi deoOutOpti mal CT (ClockRate);

Arguments ClockRate: The frequency of the clock in the clock domain of the call to

Pal Vi deoOutRun(), in units of Hertz.

Return value Constant Pal Handl e evaluated at compile time.

Description Returns the handle the optimal video output display for a given clock

frequency, at compile time. Typically this will be the video mode that results in output closest to the standard 4:3 ratio, and therefore the

most square pixels.

macro expr Pal Vi deoOutGetMaxXWi dthCT ();

see macro expr Pal Vi deol nGetMaxXWi dthCT ();



macro expr Pal Vi deoOutGetMaxYWi dthCT ();

see macro expr Pal Vi deol nGetMaxYWi dthCT ();

macro expr Pal Vi deoOutGetMaxCol orWi dthCT ();

see macro expr Pal Vi deol nGetMaxCol orWi dthCT ();

macro expr Pal Vi deoOutGetXWi dth (Handle);

see macro expr Pal Vi deol nGetXWi dth (Handle);

macro expr Pal Vi deoOutGetYWi dth (Handle);

see macro expr Pal Vi deol nGetYWi dth (Handle);

macro expr Pal Vi deoOutGetCol orWi dth (Handle);

see macro expr Pal Vi deol nGetCol orWi dth (Handle);

macro expr Pal Vi deoOutGetXWi dthCT (HandleCT);

see macro expr Pal Vi deol nGetXWi dthCT (HandleCT);

macro expr Pal Vi deoOutGetYWi dthCT (HandleCT);

see macro expr Pal Vi deol nGetYWi dthCT (HandleCT);

macro expr Pal Vi deoOutGetCol orWi dthCT (HandleCT);

see macro expr Pal Vi deol nGetCol orWi dthCT (HandleCT);

macro expr Pal Vi deoOutGetVi si bl eX (Handle, ClockRate);

Arguments *Handl e*: Pal Handl e to a VideoOut resource.

ClockRate: The frequency of the clock in the clock domain of the call to

Pal Vi deoOutRun(), in units of Hertz.

Return value Integer value evaluated at runtime.

Description Returns the actual horizontal resolution of the video output device used

by the handle referred to, at runtime. Since this method works at runtime it can be used even when *Handle* is not a constant (such as when it is passed through a function parameter). However, it cannot be

used to set the width of variables.

macro expr Pal Vi deoOutGetVi si bl eY (Handle);

Arguments Handle: Pal Handle to a VideoOut resource.

Return value

Integer value evaluated at runtime.

Description Returns the actual vertical resolution of the video output device used by

the handle referred to, at runtime. Since this method works at runtime it can be used even when *Handle* is not a constant (such as when it is passed through a function parameter). However, it cannot be used to set

the width of variables.



macro expr Pal Vi deoOutGetTotal X (Handle, ClockRate);

Arguments *Handle*: Pal Handle to a VideoOut resource.

ClockRate: The frequency of the clock in the clock domain of the call to

Pal Vi deoOutRun(). In units of Hertz.

Return value Integer value evaluated at runtime.

Description Returns the actual total number of columns (including the blanking

period) of the video output device used by the handle referred to, at runtime. Since this method works at runtime it can be used even when *Handle* is not a constant (such as when it is passed through a function parameter). However, it cannot be used to set the width of variables.

macro expr Pal Vi deoOutGetTotal Y (Handle);

Arguments Handle: Pal Handle to a VideoOut resource.

Return value Integer value evaluated at runtime.

Description Returns the actual total number of rows (including the blanking period)

of the video output device used by the handle referred to, at runtime. Since this method works at runtime it can be used even when *Handle* is not a constant (such as when it is passed through a function parameter).

However, it cannot be used to set the width of variables.

macro expr Pal Vi deoOutGetVi si bl eXCT (Handl eCT, Cl ockRate);

Arguments *Handl eCT*: constant Pal Handl e to a VideoOut resource.

ClockRate: The frequency of the clock in the clock domain of the call to

Pal Vi deoOutRun(). In units of Hertz.

Return value Integer compile-time constant.

Description Returns the actual horizontal resolution of the video output device that is

used by the handle referred to, at compile time. Since this method works at compile time it can *only* be used where *Handl eCT* is a constant, and can be deduced to be a constant by the DK compiler. So for instance, this cannot be used if *Handl eCT* is passed through a function parameter. However, since it returns a compile time constant it can be used to set

variable widths and do conditional compilation (using select and

ifselect).



macro expr Pal Vi deoOutGetVi si bl eYCT (Handl eCT);

Arguments Handl eCT: constant Pal Handl e to a VideoOut resource

Return value Integer compile-time constant.

Description Returns the actual vertical resolution of the video output device that is

used by the handle referred to, at compile time. Since this method works at compile time it can only be used where *HandleCT* is a constant, and can be deduced to be a constant by the DK compiler. So for instance, this cannot be used if *HandleCT* is passed through a function parameter. However, since it returns a compile time constant it can be used to set variable widths and do conditional compilation (using select and

ifselect)

macro expr Pal Vi deoOutGetTotal XCT (HandleCT, ClockRate);

Arguments *Handl eCT*: constant Pal Handl e to a VideoOut resource.

ClockRate: The frequency of the clock in the clock domain of the call to

Pal Vi deoOutRun. In units of Hertz.

Return value Integer compile-time constant.

Description Returns the actual total number of columns (including blanking period) of

the video output device that is used by the handle referred to, at compile time. Since this method works at compile time it can *only* be used where Handl eCT is a constant, and can be deduced to be a constant by the DK compiler. So for instance, this cannot be used if Handl eCT is passed through a function parameter. However, since it returns a compile time

constant it can be used to set variable widths and do conditional

compilation (using sel ect and i fsel ect)

macro expr Pal Vi deoOutGetTotal YCT (Handl eCT);

Arguments Handl eCT: constant Pal Handl e to a VideoOut resource.

Return value Integer compile-time constant.

Description Returns the actual total number of rows (including blanking period) of

the video output device that is used by the handle referred to, at compile time. Since this method works at compile time it can only be used where <code>HandleCT</code> is a constant, and can be deduced to be a constant by the DK compiler. So for instance, this cannot be used if <code>HandleCT</code> is passed through a function parameter. However, since it returns a compile time constant it can be used to set variable widths and do conditional

compilation (using sel ect and i fsel ect)

macro proc Pal Vi deoOutRun (HandleCT, ClockRate);

see macro proc Pal XRun (HandleCT, ClockRate);



macro proc Pal Vi deoOutReset (Handle);

see macro proc Pal XReset (Handle);

macro proc Pal Vi deoOutEnable (Handle);

see macro proc Pal XEnable (Handle);

macro proc Pal Vi deoOutDi sable (Handle);

see macro proc Pal XDi sable (Handle);

macro expr Pal Vi deoOutGetX (Handle);

Arguments Handle: Pal Handle to a VideoOut resource.

Return value unsigned int (Pal Vi deoOutGetMaxXWi dthCT ())

Description Returns the current horizontal scan position of the screen output. A call

to Pal Vi deoOutWri te() will write a pixel to position on the video output

device returned by this method and Pal Vi deoOutGetY().

macro expr Pal Vi deoOutGetY (Handle);

Arguments *Handl e*: Pal Handl e to a VideoOut resource.

Return value unsigned int (Pal Vi deoOutGetMaxYWi dthCT ()).

Description Returns the current horizontal scan position of the screen output. A call

to Pal Vi deoOutWri te() will write a pixel to position on the video output

device returned by this method and Pal Vi deoOutGetX().

macro expr Pal Vi deoOutGetHBl ank (Handle);

Arguments Handle: Pal Handle to a VideoOut resource.

Return value unsigned 1.

Description Returns the horizontal blanking status of the current scan position. A

return value of 1 means the scan position is inside the blanking portion of the display. A return value of 0 means the scan position is inside the

visible portion of the display.

macro expr Pal Vi deoOutGetVBI ank (Handle);

Arguments *Handl e*: Pal Handl e to a VideoOut resource.

Return value unsi gned 1.

Description Returns the vertical blanking status of the current scan position. A return

value of 1 means the scan position is inside the blanking portion of the display. A return value of 0 means the scan position is inside the visible

portion of the display.



macro proc Pal Vi deoOutWri te (Handle, Pi xel);

Arguments Handle: Pal Handle to a VideoOut resource.

Pi xel: An expression of type unsi gned
(Pal Vi deoOutGetMaxCol orWi dthCT ()).

Timing 1 clock cycle.

Description Writes a single pixel value to the video output device at the current scan

position, which can be obtained using the methods Pal Vi deoOutGetX()

and Pal Vi deoOutGetY().

3.15 Audio input devices (Audio In API)

The AudioIn API supports generic audio input devices.

macro expr Pal Audi ol n (Index);

see macro expr Pal X (*Index*);

macro expr Pal Audi ol nCT (Index);

see macro expr Pal XCT (Index);

macro expr Pal Audi ol nCount ();

see macro expr Pal XCount ();

macro expr Pal Audi ol nUni queCount ();

see macro expr Pal XUni queCount ();

macro proc Pal Audi ol nRequire (Count);

see macro expr Pal XRequire (Count);

macro expr Pal Audi ol nGetMaxDataWi dthCT ();

see macro expr Pal XGetMaxDataWidthCT ();

macro expr Pal Audi ol nGetDataWi dth (Handle);

see macro expr Pal XGetDataWidth (Handle);

macro expr Pal Audi ol nGetDataWi dthCT (Handl eCT);

see macro expr Pal XGetDataWidthCT (HandleCT);

macro proc Pal Audi ol nRun (HandleCT, ClockRate);

see macro proc Pal XRun (HandleCT, ClockRate);

macro proc Pal Audi ol nReset (Handle);

see macro proc Pal XReset (Handle);

macro proc Pal Audi ol nEnabl e (Handle);

see macro proc Pal XEnable (Handle);

macro proc Pal Audi ol nDi sable (Handle);

see macro proc Pal XDi sable (Handle);



macro proc Pal Audi ol nSetSampl eRate (Handle, SampleRate);

Arguments *Handl e*: Pal Handl e to an AudioIn resource.

SampleRate: integer constant, equal to the number of samples per

second that the input device should generate.

Timing 1 or more clock cycles.

Description Sets the sample rate of the audio input device. If the sample rate

requested is not supported by the device then the rate is left unchanged.

macro proc Pal Audi ol nRead (Handle, LeftPtr, RightPtr);

Arguments Handle: Pal Handle to an Audioln resource.

LeftPtr, RightPtr: Expressions of type signed

(Pal Audi ol nGetMaxDataWi dthCT ()).

Timing 1 or more clock cycles.

Description Reads a stereo pair of samples from the audio input device. Will block

until the device has a new sample. If Pal Audi ol nRead() is not called

quickly enough, some samples may be missed.

3.16 Audio output devices (AudioOut API)

The AudioOut API supports generic audio output devices.

macro expr Pal Audi oOut (Index);

see macro expr Pal X (Index);

macro expr Pal Audi oOutCT (Index);

see macro expr Pal XCT (Index);

macro expr Pal Audi oOutCount ();

see macro expr Pal XCount ();

macro expr Pal Audi oOutUni queCount ();

see macro expr Pal XUni queCount ();

macro proc Pal Audi oOutRequi re (Count);

see macro expr Pal XRequire (Count);

macro expr Pal Audi oOutGetMaxDataWi dthCT ();

see macro expr Pal XGetMaxDataWidthCT ();

macro expr Pal Audi oOutGetDataWi dth (Handle);

see macro expr Pal XGetDataWidth (Handle);

macro expr Pal Audi oOutGetDataWi dthCT (Handl eCT);

see macro expr Pal XGetDataWidthCT (HandleCT);



macro proc Pal Audi oOutRun (HandleCT, ClockRate);

see macro proc Pal XRun (HandleCT, ClockRate);

macro proc Pal Audi oOutReset (Handle);

see macro proc Pal XReset (Handle);

macro proc Pal Audi oOutEnable (Handle);

see macro proc Pal XEnable (Handle);

macro proc Pal Audi oOutDi sable (Handle);

see macro proc Pal XDi sable (Handle);

macro proc Pal Audi oOutSetSampl eRate (Handle, SampleRate);

Arguments Handle: Pal Handle to an AudioOut resource.

SampleRate: integer constant, equal to the number of samples per

second that the output device should expect.

Timing 1 or more clock cycles.

Description Sets the sample rate of the audio output device. If the sample rate

requested is not supported by the device then the rate is left unchanged.

macro proc Pal Audi oOutWri te (Handle, Left, Right);

Arguments Handle: Pal Handle to an AudioOut resource.

Left, Right: Expressions of type signed (Pal Audi oOutGetMaxDataWi dthCT ()).

Timing 1 or more clock cycles.

Description Writes a stereo pair of samples to the audio output device. Will block

until the device is ready to accept a new sample. If Pal Audi oOutWri te()

is not called quickly enough, gaps may occur in the audio output.

3.17 Ethernet devices (Ethernet API)

The Ethernet API supports generic Ethernet interface devices.

macro expr Pal Ethernet (Index);

see macro expr Pal X (*Index*);

macro expr Pal EthernetCT (Index);

see macro expr Pal XCT (Index);

macro expr Pal EthernetCount ();

see macro expr Pal XCount ();

macro expr Pal EthernetUni queCount ();

see macro expr Pal XUni queCount ();



macro proc Pal EthernetRequi re (Count);

see macro expr Pal XRequire (Count);

macro proc Pal EthernetRun (HandleCT, MACAddress, ClockRate);

Arguments *Handl eCT*: constant Pal Handl e to a PalEthernet resource.

MACAddress: Ethernet MAC address to be used by the network chip, of

type unsigned 48.

ClockRate: Clock rate of the clock domain of call to this macro, in Hz.

Timing Does not terminate in normal use.

Description Runs the device management tasks for the Ethernet interface. Must

always run in parallel with accesses to the device.

macro proc Pal EthernetReset (Handle);

see macro proc Pal XReset (Handle);

macro proc Pal EthernetEnabl e (Handle);

see macro proc Pal XEnable (Handle);

macro proc Pal EthernetDi sable (Handle);

see macro proc Pal XDi sable (Handle);

macro proc Pal EthernetReadBegi n (Handle, DestinationPtr, SourcePtr, TypePtr, DataByteCountPtr, ErrorPtr);

Arguments Handle: Pal Handle to a PalEthernet resource.

DestinationPtr: Pointer to data of type unsigned 48. Will return the destination MAC address from the received packet.

SourcePtr: Pointer to data of type unsigned 48. Will return the source MAC address from the received packet.

TypePtr: Pointer to data of type unsigned 16. Will return the type of the received packet.

DataByteCountPtr: Pointer to data of type unsigned 11. Will return the number of data bytes in the received packet, excluding the header.

ErrorPtr: Pointer to data of type unsigned 1. Returns success = 0, failure = 1.

Timing 1 or more clock cycles.

Description Checks to see if a packet is waiting to be read, and if it is initiates the

read process and returns source, destination, etc. This must be followed by calls to Pal EthernetRead() to get the data from the packet, and Pal EthernetReadEnd() to complete the process. If no packet is waiting to be read, the macro will return *ErrorPtr* as 1, indicating an error.



macro proc Pal EthernetRead (Handle, DataPtr, ErrorPtr);

Arguments Handle: Pal Handle to a PalEthernet resource.

DataPtr: Pointer to data of type unsigned 8. Will return a byte of data

from the received packet.

ErrorPtr: Pointer to data of type unsigned 1. Returns success = 0,

failure = 1.

Timing One or more clock cycles.

Description Returns a single data byte from the packet currently being read. Will

return ErrorPtr = 1, indicating an error, if it is called when there is no

data remaining in the packet.

macro proc Pal EthernetReadEnd (Handle, ErrorPtr);

Arguments *Handl e*: Pal Handl e to a PalEthernet resource.

ErrorPtr: Pointer to data of type unsigned 1. Returns success = 0,

failure = 1.

Timing One or more clock cycles.

Description Completes the process of reading a packet from the Ethernet device.

Must be called after all data has been read from a packet.

macro proc Pal EthernetWri teBegin (Handle, Destination, Type,
DataByteCount, ErrorPtr);

Arguments Handle: Pal Handle to a PalEthernet resource.

Destination: Data of type unsigned 48. Specifies the destination MAC

address for the packet.

Type: Data of type unsigned 16. Specifies the type of the outgoing

packet.

DataByteCount: Data of type unsigned 11. Specifies the number of data

bytes to be sent, excluding the header.

ErrorPtr: Pointer to data of type unsigned 1. Returns success = 0,

failure = 1.

Timing One or more clock cycles.

Description Initiates a packet write operation, to send data to the network via the

Ethernet device. *Destination* is the MAC address to send the packet to, and *DataByteCount* is the number of data bytes to be sent, which must be in the range 46-1500 for Ethernet. *ErrorPtr* will be set to 0 if the call

was successful, and 1 otherwise.



macro proc Pal EthernetWri te (Handle, Data, ErrorPtr);

Arguments *Handl e*: Pal Handl e to a PalEthernet resource.

Data: Data of type unsigned 8, containing a byte of data to write to the

packet.

ErrorPtr: Pointer to data of type unsigned 1. Returns success = 0,

failure = 1.

Timing One or more clock cycles.

Description Writes a single byte to the Ethernet device, to be added to the packet

currently being written. Will return ErrorPtr = 1, indicating an error, if called when the expected number of bytes has already been written to

the packet.

macro proc Pal EthernetWri teEnd (Handle, ErrorPtr);

Arguments *Handl e*: Pal Handl e to a PalEthernet resource.

ErrorPtr: Pointer to data of type unsigned 1. Returns success = 0,

failure = 1.

Timing One or more clock cycles.

Description Completes the process of sending a packet. Must be called after all data

has been written to a packet.



Index

API		generic	22
audio input	35	pipelined	18, 20
audio output	36	PL1	18
block storage	24	PL2	20
buttons	13	single cycle 16	, 18, 20
data I/O	14	slow RAM	22
Ethernet	37	pal.hch	5
LED macros	12	PalAudioIn	35
parallel port	15	PalAudioInCount	35
PS/2 ports	16	PalAudioInCT	35
RAM	16, 18, 20, 22	PalAudioInDisable	35
resource handles	6	PalAudioInEnable	35
RS-232	15	PalAudioInGetDataWidth	35
serial ports	15, 16	PalAudioInGetMaxDataWidthCT	35
seven-segment	12	PalAudioInRead	36
switches	13	PalAudioInRequire	35
version numbers	6	PalAudioInReset	35
video input	26	PalAudioInRun	35
video output	30	PalAudioInSetSampleRate	36
audio input API	35	PalAudioInUniqueCount	35
audio output API	36	PalAudioOut	36
buttons API	13	PalAudioOutCount	36
data I/O API	14	PalAudioOutCT	36
errors		PalAudioOutDisable	37
detecting	8	PalAudioOutEnable	37
Ethernet API	37	PalAudioOutGetMaxDataWidthCT	36
header files	5	PalAudioOutRequire	36
ID codes	7	PalAudioOutReset	37
LED API	12	PalAudioOutRun	37
library files	5	PalAudioOutSetSampleRate	37
memory		PalAudioOutUniqueCount	36
block	24	PalAudioOutWrite	37
fast RAM	16	PalBlockStore	24
Flash	24	PalBlockStoreCount	24



PalBlockStoreCT	24	PalEthernetDisable	38
PalBlockStoreDisable	25	PalEthernetEnable	38
PalBlockStoreEnable	25	PalEthernetRead	39
PalBlockStoreEraseBlock	26	PalEthernetReadBegin	38
PalBlockStoreGetAddressWidth	25	PalEthernetReadEnd	39
PalBlockStoreGetAddressWidthCT	25	PalEthernetRequire	38
PalBlockStoreGetBlockLength	25	PalEthernetReset	38
PalBlockStoreGetBlockLengthCT	25	PalEthernetRun	38
PalBlockStoreGetDataWidth	25	PalEthernetUniqueCount	37
PalBlockStoreGetDataWidthCT	25	PalEthernetWrite	40
PalBlock Store Get Max Address Width CT	24	PalEthernetWriteBegin	39
PalBlockStoreGetMaxBlockLengthCT	24	PalEthernetWriteEnd	40
PalBlockStoreGetMaxDataWidthCT	24	PalFastRAM	16
PalBlockStoreRead	25	PalFastRAMCount	16
PalBlockStoreRequire	24	PalFastRAMCT	16
PalBlockStoreReset	25	PalFastRAMDisable	18
PalBlockStoreRun	25	PalFastRAMEnable	18
PalBlockStoreUniqueCount	24	PalFastRAMGetAddressWidth	17
PalBlockStoreWrite	26	PalFastRAMGetAddressWidthCT	17
PalDataPort	14	PalFastRAMGetDataWidth	17
PalDataPortCount	14	PalFastRAMGetDataWidthCT	17
PalDataPortCT	14	PalFastRAMGetMaxAddressWidthCT	17
PalDataPortDisable	14	PalFastRAMGetMaxDataWidthCT	17
PalDataPortEnable	14	PalFastRAMRead	18
PalDataPortGetDataWidth	14	PalFastRAMRequire	17
PalDataPortGetDataWidthCT	14	PalFastRAMReset	18
PalDataPortGetMaxDataWidthCT	14	PalFastRAMRun	17
PalDataPortRead	15	PalFastRAMUniqueCount	16
PalDataPortRequire	14	PalFastRAMWrite	18
PalDataPortReset	14	PalHandle	6
PalDataPortRun	14	PalLED	12
PalDataPortUniqueCount	14	PalLEDCount	12
PalDataPortWrite	15	PalLEDCT	12
PalErrorCode	8	PalLEDRequire	12
PalErrorHandlerRun	8	PalLEDUniqueCount	12
PalEthernet	37	PalLEDWrite	12
PalEthernetCount	37	PalParallelPort	15
PalEthernetCT	37	PalParallelPortCount	15



PalParallelPortCT	15	PaIPL2RAMSetWriteAddress	22
PalParallelPortRequire	15	PaIPL2RAMUniqueCount	21
PalParallelPortUniqueCount	15	PaIPL2RAMWrite	22
PaIPL1RAM	18	PaIPS2Port	16
PaIPL1RAMCount	18	PaIPS2PortCount	16
PaIPL1RAMCT	18	PaIPS2PortCT	16
PaIPL1RAMDisable	19	PaIPS2PortRequire	16
PalPL1RAMEnable	19	PalPS2PortUniqueCount	16
PaIPL1RAMGetAddressWidth	19	PaIRS232Port	15
PaIPL1RAMGetAddressWidthCT	19	PaIRS232PortCount	16
PalPL1RAMGetDataWidth	19	PaIRS232PortCT	16
PalPL1RAMGetDataWidthCT	19	PaIRS232PortRequire	16
PaIPL1RAMGetMaxAddressWidthCT	19	PaIRS232PortUniqueCount	16
PalPL1RAMGetMaxDataWidthCT	19	PalSevenSeg	12
PaIPL1RAMPortRequire	19	PalSevenSegCount	12
PaIPL1RAMRead	20	PalSevenSegCT	12
PaIPL1RAMReset	19	PalSevenSegDisable	13
PalPL1RAMRun	19	PalSevenSegEnable	13
PaIPL1RAMSetReadAddress	19	PalSevenSegRequire	13
PaIPL1RAMSetWriteAddress	20	PalSevenSegUniqueCount	12
PaIPL1RAMUniqueCount	19	PalSevenSegWriteDigit	13
PaIPL1RAMWrite	20	PalSevenSegWriteShape	13
PaIPL2RAM	20	PalSlowRAM	22
PaIPL2RAMCount	20	PalSlowRAMCount	22
PaIPL2RAMCT	20	PalSlowRAMCT	22
PaIPL2RAMDisable	21	PalSlowRAMDisable	23
PaIPL2RAMEnable	21	PalSlowRAMEnable	23
PaIPL2RAMGetAddressWidth	21	PalSlowRAMGetAddressWidth	23
PaIPL2RAMGetAddressWidthCT	21	PalSlowRAMGetAddressWidthCT	23
PaIPL2RAMGetDataWidth	21	PalSlowRAMGetDataWidth	23
PaIPL2RAMGetDataWidthCT	21	PalSlowRAMGetDataWidthCT	23
PaIPL2RAMGetMaxAddressWidthCT	21	PalSlowRAMGetMaxAddressWidthCT	23
PaIPL2RAMGetMaxDataWidthCT	21	PalSlowRAMGetMaxDataWidthCT	23
PaIPL2RAMPortRequire	21	PalSlowRAMRead	23
PaIPL2RAMRead	22	PalSlowRAMRequire	23
PaIPL2RAMReset	21	PalSlowRAMReset	23
PaIPL2RAMRun	21	PalSlowRAMRun	23
PaIPL2RAMSetReadAddress	21	PalSlowRAMUniqueCount	23



PalSlowRAMWrite	24	PalVideoOutGetColorWidthCT	31
PalSwitch	13	PalVideoOutGetHBlank	34
PalSwitchCount	13	PalVideoOutGetMaxColorWidthCT	31
PalSwitchCT	13	PalVideoOutGetMaxXWidthCT	30
PalSwitchRead	14	PalVideoOutGetMaxYWidthCT	31
PalSwitchRequire	14	PalVideoOutGetTotalX	32
PalSwitchUniqueCount	13	PalVideoOutGetTotalXCT	33
PalVendorCode	7	PalVideoOutGetTotalY	32
PalVendorRelease	7	PalVideoOutGetTotalYCT	33
PalVendorString	7	PalVideoOutGetVBlank	34
PalVersionMajor	6	PalVideoOutGetVisibleX	31
PalVersionMinor	6	PalVideoOutGetVisibleXCT	32
PalVersionRequire	7	PalVideoOutGetVisibleY	31
PalVideoIn	26	PalVideoOutGetVisibleYCT	33
PalVideoInCount	26	PalVideoOutGetX	34
PalVideoInCT	26	PalVideoOutGetXWidth	31
PalVideoInDisable	29	PalVideoOutGetXWidthCT	31
PalVideoInEnable	29	PalVideoOutGetY	34
PalVideoInGetColorWidth	28	PalVideoOutGetYWidth	31
PalVideoInGetColorWidthCT	29	PalVideoOutGetYWidthCT	31
PalVideoInGetMaxColorWidthCT	27	PalVideoOutOptimalCT	30
PalVideoInGetMaxXWidthCT	27	PalVideoOutRequire	30
PalVideoInGetMaxYWidthCT	27	PalVideoOutReset	34
PalVideoInGetXWidth	27	PalVideoOutRun	33
PalVideoInGetXWidthCT	28	PalVideoOutUniqueCount	30
PalVideoInGetYWidth	28	PalVideoOutWrite	35
PalVideoInGetYWidthCT	29	PalX	9
PalVideoInRead	30	PalXCount	8
PalVideoInRequire	27	PalXCT	9
PalVideoInReset	29	PalXDisable	11
PalVideoInRun	29	PalXEnable	11
PalVideoInUniqueCount	27	PalXGetDataWidth	10
PalVideoOut	30	PalXGetDataWidthCT	10
PalVideoOutCount	30	PalXGetMaxDataWidthCT	9
PalVideoOutCT	30	PalXRead	11
PalVideoOutDisable	34	PalXRequire	9
PalVideoOutEnable	34	PalXReset	10
PalVideoOutGetColorWidth	31	PalXRun	10





PalXUniqueCount	9	properties	9
PalXWrite	11	reading from	11
parallel port API	15	resetting	10
PS/2 API	16	running	10
RAM		writing to	11
pipelined	18, 20	RS-232 API	15
PL1	18	serial ports API	15, 16
PL2	20	seven-segment API	12
single cycle	16, 18, 20	switches API	13
RAM API	16, 18, 20, 22	vendor ID codes	7
resetting resources	10	version numbers	
resources		API	6
enabling and disabling	11	libraries	7
handles	6, 9	video input API	26
number of	8	video output API	30

Customer Support at http://www.celoxica.com/support/

Celoxica in Europe Celoxica in Japan Celoxica in Asia Pacific Celoxica in the Americas

Copyright © 2003 Celoxica Ltd. All rights reserved. Celoxica, the Celoxica logo and Handel-C are trademarks of Celoxica Limited. All other trademarks acknowledged. The information herein is subject to change and for quidance only